MODBUS POINT MAP

All Variables are in integer format.

<u>Int</u>	<u>R/W</u>	NV	Description
Regis	ters	1-42	are in milliamps (10000 = 10.000Amps)
1	R		Current, Channel 1
2	R		Current, Channel 2
3	R		Current, Channel 3
4	R		Current, Channel 4
5	R		Current, Channel 5
6	R		Current, Channel 6
7	R		Current, Channel 7
8	R		Current, Channel 8
9	R		Current, Channel 9
10	R		Current, Channel 10
11	R		Current, Channel 11
12	R		Current, Channel 12
13	R		Current, Channel 13
14	R		Current, Channel 14
15	R		Current, Channel 15
16	R		Current, Channel 16
17	R		Current, Channel 17
18	R		Current, Channel 18
19	R		Current, Channel 19
20	R		Current, Channel 20
21	R		Current, Channel 21
22	R		Current, Channel 22
23	R		Current, Channel 23
24	R		Current, Channel 24
25	R		Current, Channel 25
26	R		Current, Channel 26
27	R		Current, Channel 27
28	R		Current, Channel 28
29	R		Current, Channel 29
30	R		Current, Channel 30
31	R		Current, Channel 31
32	R		Current, Channel 32
33	R		Current, Channel 33
34	R		Current, Channel 34
35	R		Current, Channel 35
36	R		Current, Channel 36
37	R		Current, Channel 37
38	R		Current, Channel 38
39	R		Current, Channel 39
40	R		Current, Channel 40
41	R		Current, Channel 41
42	R		Current, Channel 42

Page 1 of 13 05/29/01

Int R/W NV Description 43 R NV Global Warning/Critical Alarm Registers

This register provides a quick status of alarms for the unit. A bit in this register is set if any bit in the indicated register is set.

bit 0: Warning Register 1 bit 1: Warning Register 2 bit 2: Warning Register 3 bit 3: Critical Register 1 bit 4: Critical Register 2 bit 5: Critical Register 3 bit 6: Error Register bits 7-15: Always read as 0

The following Warning Registers set a bit for every channel which reads a current above the Warning Threshold but below the Critical Threshold for at least the Warning Time-Delay. All alarms are latching and must be reset by the controller. To reset any alarm, read the register and then write the register with the desired alarm bit cleared.

44 R/W NV Warning Register 1

bit 0: Channel 1 bit 1: Channel 2 bit 2: Channel 3 bit 3: Channel 4 bit 4: Channel 5 bit 5: Channel 6 bit 6: Channel 7 bit 7: Channel 8 bit 8: Channel 9 bit 9: Channel 10 bit 10: Channel 11 bit 11: Channel 12 bit 12: Channel 13 bit 13: Channel 14 bit 14: Channel 15 bit 15: Channel 16

```
R/W
           NV
                 Description
45
                  Warning Register 2
     R/W
           NV
                 bit 0:
                         Channel 17
                 bit 1: Channel 18
                 bit 2: Channel 19
                         Channel 20
                 bit 3:
                 bit 4: Channel 21
                 bit 5: Channel 22
                 bit 6: Channel 23
                 bit 7: Channel 24
                 bit 8: Channel 25
                 bit 9: Channel 26
                 bit 10: Channel 27
                 bit 11: Channel 28
                 bit 12: Channel 29
                 bit 13: Channel 30
                 bit 14: Channel 31
                 bit 15: Channel 32
46
     R/W
                 Warning Register 3
           NV
                 bit 0:
                         Channel 33
                 bit 1:
                         Channel 34
                 bit 2: Channel 35
                 bit 3: Channel 36
                 bit 4: Channel 37
                 bit 5:
                         Channel 38
                 bit 6: Channel 39
                 bit 7: Channel 40
                 bit 8: Channel 41
                 bit 9: Channel 42
                 bits 10-15: Always read as 0
```

The following Critical Registers set a bit for every channel which reads a current above the Critical Threshold for at least the Critical Time-Delay. All alarms are latching and must be reset by the controller. To reset any alarm, read the register and then write the register with the desired alarm bit cleared.

```
47
     R/W
           NV
                 Critical Alarm Register 1
                 bit 0: Channel 1
                 bit 1: Channel 2
                 bit 2: Channel 3
                 bit 3: Channel 4
                 bit 4: Channel 5
                 bit 5:
                         Channel 6
                 bit 6:
                         Channel 7
                 bit 7:
                         Channel 8
                 bit 8: Channel 9
                 bit 9: Channel 10
                 bit 10: Channel 11
                 bit 11: Channel 12
                 bit 12: Channel 13
                 bit 13: Channel 14
                 bit 14: Channel 15
                 bit 15: Channel 16
```

```
# R/W
                 Description
           NV
48
     R/W
           NV
                 Critical Alarm Register 2
                 bit 0: Channel 17
                 bit 1: Channel 18
                 bit 2: Channel 19
                 bit 3: Channel 20
                 bit 4: Channel 21
                 bit 5: Channel 22
                 bit 6: Channel 23
                 bit 7: Channel 24
                 bit 8: Channel 25
                 bit 9: Channel 26
                 bit 10: Channel 27
                 bit 11: Channel 28
                 bit 12: Channel 29
                 bit 13: Channel 30
                 bit 14: Channel 31
                 bit 15: Channel 32
49
     R/W NV
                 Critical Alarm Register 3
                        Channel 33
                 bit 0:
                 bit 1: Channel 34
                 bit 2: Channel 35
                 bit 3: Channel 36
                 bit 4: Channel 37
                 bit 5: Channel 38
                 bit 6: Channel 39
                 bit 7: Channel 40
                 bit 8: Channel 41
                 bit 9: Channel 42
                 bits 10-15: Always read as 0
50
    R
         NV
                 Firmware Version
51
           NV
                 Firmware Revision
```

05/29/01

R/W NV Description

The following Breaker Size registers set the capacity of each breaker for the alarms. These settings should match the CT with its associated breaker's rating. Units are in Amps (10 = 10Amps). Range = 10 to 50. Defaults are all set to 20.

52	R/W	NV	Breaker	Size	Channel	1
53	R/W	NV	Breaker	Size	Channel	2
54	R/W	NV	Breaker	Size	Channel	3
55	R/W	NV	Breaker	Size	Channel	4
56	R/W	NV	Breaker	Size	Channel	5
57	R/W	NV	Breaker	Size	Channel	6
58	R/W	NV	Breaker	Size	Channel	7
59	R/W	NV	Breaker	Size	Channel	8
60	R/W	NV	Breaker	Size	Channel	9
61	R/W	NV	Breaker	Size	Channel	10
62	R/W	NV	Breaker	Size	Channel	11
63	R/W	NV	Breaker	Size	Channel	12
64	R/W	NV	Breaker	Size	Channel	13
65	R/W	NV	Breaker	Size	Channel	14
66	R/W	NV	Breaker	Size	Channel	15
67	R/W	NV	Breaker	Size	Channel	16
68	R/W	NV	Breaker	Size	Channel	17
69	R/W	NV	Breaker	Size	Channel	18
70	R/W	NV	Breaker	Size	Channel	19
71	R/W	NV	Breaker	Size	Channel	20
72	R/W	NV	Breaker	Size	Channel	21
73	R/W	NV	Breaker	Size	Channel	22
74	R/W	NV	Breaker	Size	Channel	23
75	R/W	NV	Breaker	Size	Channel	24
76	R/W	NV	Breaker	Size	Channel	25
77	R/W	NV	Breaker	Size	Channel	26
78	R/W	NV	Breaker	Size	Channel	27
79	R/W	NV	Breaker	Size	Channel	28
80	R/W	NV	Breaker	Size	Channel	29
81	R/W	NV	Breaker	Size	Channel	30
82	R/W	NV	Breaker	Size	Channel	31
83	R/W	NV	Breaker	Size	Channel	32
84	R/W	NV	Breaker	Size	Channel	33
85	R/W	NV	Breaker	Size	Channel	34
86	R/W	NV	Breaker	Size	Channel	35
87	R/W	NV	Breaker	Size	Channel	36
88	R/W	NV	Breaker	Size	Channel	37
89	R/W	NV	Breaker	Size	Channel	38
90	R/W	NV	Breaker	Size	Channel	39
91	R/W	NV	Breaker	Size	Channel	40
92	R/W	NV	Breaker	Size	Channel	41
93	R/W	NV	Breaker	Size	Channel	42

R/W NV Description

The following Warning Threshold registers set the thresholds for the Warning alarms as a percentage of the breaker size registers (52-93). A Warning alarm will occur if the measured current is above the Warning Threshold but below the Critical alarm Threshold for at least the Warning Time Delay. Units are in percent (75 = 75%). Range is 0-100. Default setting is 60%. Note that a Warning will not always be generated if the current instantaneously jumps from below the Warning Threshold to above the Critical alarm Threshold.

94	R/W	NV	Warning	Threshold	Channel	1
95	R/W	NV	Warning	Threshold	Channel	2
96	R/W	NV	Warning	Threshold	Channel	3
97	R/W	NV	Warning	Threshold	Channel	4
98	R/W	NV	Warning	Threshold	Channel	5
99	R/W	NV	Warning	Threshold	Channel	6
100	R/W	NV	Warning	Threshold	Channel	7
101	R/W	NV	Warning	Threshold	Channel	8
102	R/W	NV	Warning	Threshold	Channel	9
103	R/W	NV	Warning	Threshold	Channel	10
104	R/W	NV	Warning	Threshold	Channel	11
105	R/W	NV	Warning	Threshold	Channel	12
106	R/W	NV	Warning	Threshold	Channel	13
107	R/W	NV	Warning	Threshold	Channel	14
108	R/W	NV	Warning	Threshold	Channel	15
109	R/W	NV	Warning	Threshold	Channel	16
110	R/W	NV	Warning	Threshold	Channel	17
111	R/W	NV	Warning	Threshold	Channel	18
112	R/W	NV	Warning	Threshold	Channel	19
113	R/W	NV	Warning	Threshold	Channel	20
114	R/W	NV	Warning	Threshold	Channel	21
115	R/W	NV	Warning	Threshold	Channel	22
116	R/W	NV	Warning	Threshold	Channel	23
117	R/W	NV	Warning	Threshold	Channel	24
118	R/W	NV	Warning	Threshold	Channel	25
119	R/W	NV	Warning	Threshold	Channel	26
120	R/W	NV	Warning	Threshold	Channel	27
121	R/W	NV	Warning	Threshold	Channel	28
122	R/W	NV	Warning	Threshold	Channel	29
123	R/W	NV	Warning	Threshold	Channel	30
124	R/W	NV	Warning	Threshold	Channel	31
125	R/W	NV	Warning	Threshold	Channel	32
126	R/W	NV	Warning	Threshold	Channel	33
127	R/W	NV	Warning	Threshold	Channel	34
128	R/W	NV	Warning	Threshold	Channel	35
129	R/W	NV	Warning	Threshold	Channel	36
130	R/W	NV	Warning	Threshold	Channel	37
131	R/W	NV	Warning	Threshold	Channel	38
132	R/W	NV	Warning	Threshold	Channel	39
133	R/W	NV	Warning	Threshold	Channel	40
134	R/W	NV	Warning	Threshold	Channel	41
135	R/W	NV	Warning	Threshold	Channel	42

R/W NV Description

The following Critical alarm Threshold registers set the thresholds for the Critical alarms as a percentage of the breaker size registers (52-93). A Critical alarm will occur if the measured current is above the Critical alarm Threshold for at least the Critical alarm Time Delay. Units are in percent (75 = 75%). Range is 0-100. Default setting is 70%.

126	D /147	NTT 7	0	7 7	mbabalal	Ob a rara a 1	1
136	R/W	NV			Threshold		1
137	R/W	NV	Critical		Threshold		2
138	R/W	NV	Critical		Threshold		3
139	R/W	NV	Critical	Alarm	Threshold		4
140	R/W	NV	Critical		Threshold		5
141	R/W	NV	Critical	Alarm	Threshold		6
142	R/W	NV	Critical	Alarm	Threshold	Channel	7
143	R/W	NV	Critical	Alarm	Threshold	Channel	8
144	R/W	NV	Critical	Alarm	Threshold	Channel	9
145	R/W	NV	Critical	Alarm	Threshold	Channel	10
146	R/W	NV	Critical	Alarm	Threshold	Channel	11
147	R/W	NV	Critical	Alarm	Threshold	Channel	12
148	R/W	NV	Critical	Alarm	Threshold	Channel	13
149	R/W	NV	Critical	Alarm	Threshold	Channel	14
150	R/W	NV	Critical	Alarm	Threshold	Channel	15
151	R/W	NV	Critical	Alarm	Threshold	Channel	16
152	R/W	NV	Critical	Alarm			17
153	R/W	NV	Critical	Alarm	Threshold		18
154	R/W	NV	Critical	Alarm	Threshold	Channel	19
155	R/W	NV	Critical	Alarm	Threshold	Channel	20
156	R/W	NV	Critical	Alarm	Threshold		21
157	R/W	NV	Critical	Alarm	Threshold	Channel	22
158	R/W	NV	Critical	Alarm	Threshold	Channel	23
159	R/W	NV	Critical		Threshold		24
160	R/W	NV	Critical		Threshold		25
161	R/W	NV	Critical		Threshold		26
162	R/W	NV	Critical		Threshold		27
163	R/W	NV	Critical	Alarm	Threshold		28
164	R/W	NV	Critical		Threshold		29
165	R/W	NV	Critical		Threshold		30
166	R/W	NV			Threshold		31
167	R/W	NV	Critical		Threshold		32
168	R/W	NV	Critical		Threshold		33
169	R/W	NV	Critical		Threshold		34
170	R/W	NV	Critical		Threshold		35
171	R/W	NV	Critical	Alarm	Threshold		36
172	R/W	NV	Critical		Threshold		37
173	R/W	NV	Critical		Threshold		38
174	R/W R/W		Critical		Threshold		39
175		NV NV	Critical		Threshold		39 40
176	R/W	NV NV	Critical				
	R/W	NV NV	Critical		Threshold Threshold		41 42
177	R/W	NV	CTICICAL	HIGIII	THESHOTO	Chaillel	44

$\frac{\#}{}$ R/W NV Description

Each of the following Warning Time Delay registers set the minimum time required for the current to exist above the Warning Threshold before the Warning alarm is set. Units are in seconds. Range is 0-65535. Default is all set to 0.

178	R/W	NV	Warning		-	Channel	1
179	R/W	NV	Warning	Time		Channel	2
180	R/W	NV	Warning	Time	Delay	Channel	3
181	R/W	NV	Warning	Time	_	Channel	4
182	R/W	NV	Warning	Time		Channel	5
183	R/W	NV	Warning	Time	Delay	Channel	6
184	R/W	NV	Warning	Time	-	Channel	7
185	R/W	NV	Warning	Time	Delay	Channel	8
186	R/W	NV	Warning	Time	Delay	Channel	9
187	R/W	NV	Warning	Time	Delay	Channel	10
188	R/W	NV	Warning	Time	Delay	Channel	11
189	R/W	NV	Warning	Time	Delay	Channel	12
190	R/W	NV	Warning	Time	Delay	Channel	13
191	R/W	NV	Warning	Time	Delay	Channel	14
192	R/W	NV	Warning	Time	Delay	Channel	15
193	R/W	NV	Warning	Time	Delay	Channel	16
194	R/W	NV	Warning	Time	Delay	Channel	17
195	R/W	NV	Warning	Time	Delay	Channel	18
196	R/W	NV	Warning	Time	Delay	Channel	19
197	R/W	NV	Warning	Time	Delay	Channel	20
198	R/W	NV	Warning	Time	Delay	Channel	21
199	R/W	NV	Warning	Time	Delay	Channel	22
200	R/W	NV	Warning	Time	Delay	Channel	23
201	R/W	NV	Warning	Time	Delay	Channel	24
202	R/W	NV	Warning	Time	Delay	Channel	25
203	R/W	NV	Warning	Time	Delay	Channel	26
204	R/W	NV	Warning	Time	Delay	Channel	27
205	R/W	NV	Warning	Time	Delay	Channel	28
206	R/W	NV	Warning	Time	Delay	Channel	29
207	R/W	NV	Warning	Time	Delay	Channel	30
208	R/W	NV	Warning	Time	Delay	Channel	31
209	R/W	NV	Warning	Time	Delay	Channel	32
210	R/W	NV	Warning	Time	Delay	Channel	33
211	R/W	NV	Warning	Time	Delay	Channel	34
212	R/W	NV	Warning	Time	Delay	Channel	35
213	R/W	NV	Warning	Time	Delay	Channel	36
214	R/W	NV	Warning	Time	Delay	Channel	37
215	R/W	NV	Warning	Time	Delay	Channel	38
216	R/W	NV	Warning	Time	Delay	Channel	39
217	R/W	NV	Warning	Time	Delay	Channel	40
218	R/W	NV	Warning	Time	Delay	Channel	41
219	R/W	NV	Warning	Time	Delay	Channel	42

05/29/01

$\frac{\#}{}$ R/W NV Description

Each of the following Critical Alarm Time Delay registers set the minimum time required for the current to exist above the Critical Alarm Threshold before the Critical Alarm is set. Units are in seconds. Range is 0-65535. Default is all set to 10.

220	R/W	NV	Critical	Alarm	Time	Delay	Channel	1
221	R/W	NV	Critical	Alarm	Time	Delay	Channel	2
222	R/W	NV	Critical	Alarm	Time	Delay	Channel	3
223	R/W	NV	Critical	Alarm	Time	Delay	Channel	4
224	R/W	NV	Critical	Alarm	Time	Delay	Channel	5
225	R/W	NV	Critical	Alarm	Time	Delay	Channel	6
226	R/W	NV	Critical	Alarm	Time	Delay	Channel	7
227	R/W	NV	Critical	Alarm	Time	Delay	Channel	8
228	R/W	NV	Critical	Alarm	Time	Delay	Channel	9
229	R/W	NV	Critical	Alarm	Time	Delay	Channel	10
230	R/W	NV	Critical	Alarm	Time	Delay	Channel	11
231	R/W	NV	Critical	Alarm	Time	Delay	Channe l	12
232	R/W	NV	Critical	Alarm	Time	Delay	Channel	13
233	R/W	NV	Critical	Alarm	Time	Delay	Channel	14
234	R/W	NV	Critical	Alarm	Time	Delay	Channel	15
235	R/W	NV	Critical	Alarm	Time	Delay	Channel	16
236	R/W	NV	Critical	Alarm	Time	Delay	Channel	17
237	R/W	NV	Critical	Alarm	Time	Delay	Channel	18
238	R/W	NV	Critical	Alarm	Time	Delay	Channel	19
239	R/W	NV	Critical	Alarm	Time	Delay	Channel	20
240	R/W	NV	Critical					21
241	R/W	NV	Critical	Alarm	Time	Delay	Channel	22
242	R/W	NV	Critical	Alarm	Time	Delay	Channel	23
243	R/W	NV	Critical					24
244	R/W	NV	Critical	Alarm	Time	Delay	Channel	25
245	R/W	NV	Critical	Alarm	Time	Delay	Channel	26
246	R/W	NV	Critical	Alarm	Time	Delay	Channel	27
247	R/W	NV	Critical	Alarm	Time	Delay	Channel	28
248	R/W	NV	Critical	Alarm	Time	Delay	Channel	29
249	R/W	NV	Critical	Alarm	Time	Delay	Channel	30
250	R/W	NV	Critical	Alarm	Time	Delay	Channel	31
251	R/W	NV	Critical	Alarm	Time	Delay	Channel	32
252	R/W	NV	Critical					33
253	R/W	NV	Critical	Alarm	Time	Delay	Channel	34
254	R/W	NV	Critical					35
255	R/W	NV	Critical					36
256	R/W	NV	Critical					37
257	R/W	NV	Critical					38
258	R/W	NV	Critical			_		39
259	R/W	NV	Critical			_		40
260	R/W	NV	Critical					41
261	R/W	NV	Critical	Alarm	Time	Delay	Channel	42

Page 9 of 13 05/29/01

# 262 263	<u>R/W</u> R R	NV NV NV	Description Serial Number Most-Significant-Word Serial Number Least-Significant-Word
268	W		Global Breaker Size
			Writing this register will set all the Breaker Size registers to the value written.
269	W		Global Warning Threshold
			Writing this register will set all the Warning Threshold registers to the value written.
270	W		Global Critical Alarm Threshold
			Writing this register will set all the Critical Alarm Threshold registers to the value written.
271	W		Global Warning Time Delay
			Writing this register will set all the Warning Time Delay registers to the value written.
272	W		Global Critical Alarm Time Delay
			Writing this register will set all the Critical Alarm Time Delay registers to the value written.
274 275	R/W R/W	NV NV	Board Name: 1^{st} 2 characters (Default = 'BR') Board Name: 2^{nd} 2 characters (Default = 'D1')

The following Instantaneous Warning Registers are non-latching versions of registers 44-46. These registers set a bit for every channel which reads a current above the Warning Threshold but below the Critical Alarm Threshold for at least the Warning Time-Delay. All alarms are non-latching and the bit will be automatically reset if the current falls below the Warning Threshold for any length of time.

```
R/W
            NV
                  Description
                  Instantaneous Warning Register 1
                 bit 0:
                         Channel 1
                 bit 1: Channel 2
                 bit 2: Channel 3
                 bit 3: Channel 4
                 bit 4:
                         Channel 5
                 bit 5:
                         Channel 6
                         Channel 7
                 bit 6:
                 bit 7: Channel 8
                 bit 8: Channel 9
                 bit 9: Channel 10
                 bit 10: Channel 11
                 bit 11: Channel 12
                 bit 12: Channel 13
                 bit 13: Channel 14
                 bit 14: Channel 15
                 bit 15: Channel 16
282
     R
                 Instantaneous Warning Register 2
                 bit 0: Channel 17
                 bit 1: Channel 18
                 bit 2: Channel 19
                 bit 3: Channel 20
                 bit 4: Channel 21
                 bit 5:
                         Channel 22
                 bit 6:
                         Channel 23
                 bit 7:
                         Channel 24
                 bit 8: Channel 25
                 bit 9: Channel 26
                 bit 10: Channel 27
                 bit 11: Channel 28
                 bit 12: Channel 29
                 bit 13: Channel 30
                 bit 14: Channel 31
                 bit 15: Channel 32
283
                 Instantaneous Warning Register 3
    R
                 bit 0: Channel 33
                 bit 1:
                         Channel 34
                 bit 2: Channel 35
                 bit 3:
                         Channel 36
                 bit 4:
                         Channel 37
                 bit 5:
                         Channel 38
                 bit 6:
                         Channel 39
                 bit 7:
                         Channel 40
                 bit 8:
                         Channel 41
                 bit 9: Channel 42
                 bits 10-15: Always read as 0
```

The following Instantaneous Critical Alarm Registers are non-latching versions of registers 47-49. These registers set a bit for every channel which reads a current above the Critical Alarm Threshold for at least the Critical Alarm Time-Delay. All alarms are non-latching and the bit will be automatically reset if the current falls below the Critical Alarm Threshold for any length of time.

```
R/W
           NV
                 Description
                 Instantaneous Critical Alarm Register 1
                 bit 0: Channel 1
                 bit 1: Channel 2
                 bit 2: Channel 3
                 bit 3: Channel 4
                 bit 4: Channel 5
                 bit 5:
                         Channel 6
                 bit 6:
                         Channel 7
                 bit 7: Channel 8
                 bit 8: Channel 9
                 bit 9: Channel 10
                 bit 10: Channel 11
                 bit 11: Channel 12
                 bit 12: Channel 13
                 bit 13: Channel 14
                 bit 14: Channel 15
                 bit 15: Channel 16
285
    R
                 Instantaneous Critical Alarm Register 2
                 bit 0: Channel 17
                 bit 1: Channel 18
                 bit 2: Channel 19
                 bit 3: Channel 20
                 bit 4: Channel 21
                 bit 5: Channel 22
                 bit 6:
                         Channel 23
                 bit 7:
                         Channel 24
                 bit 8: Channel 25
                 bit 9: Channel 26
                 bit 10: Channel 27
                 bit 11: Channel 28
                 bit 12: Channel 29
                 bit 13: Channel 30
                 bit 14: Channel 31
                 bit 15: Channel 32
286
                 Instantaneous Critical Alarm Register 3
                 bit 0: Channel 33
                 bit 1: Channel 34
                 bit 2: Channel 35
                 bit 3: Channel 36
                 bit 4: Channel 37
                 bit 5:
                         Channel 38
                 bit 6: Channel 39
                 bit 7: Channel 40
                 bit 8:
                         Channel 41
                 bit 9: Channel 42
                 bits 10-15: Always read as 0
```

LEGEND

R/W: R = Read-only R/W = Read/Write

NV: Value is stored in non-volatile memory

Supported Modbus Commands

Read Holding Register (03h), Preset Single Register (06h), Report Slave ID (11h)